POISON

KEEP OUT OF REACH OF CHILDREN
READ SAFETY DIRECTIONS BEFORE OPENING OR USING

KENSO AGCARE

BIFENTHRIN

TERMITICIDE & INSECTICIDE

ACTIVE CONSTITUENT: 100 g/L BIFENTHRIN SOLVENT: 567.5 g/L LIQUID HYDROCARBONS 50 g/L N-METHYL-2-PYRROLIDONE

GROUP 3A INSECTICIDE

For the protection of structures from subterranean termite damage, for the control of termites and a range of other urban pests, and for the control of various insect and mite pests in a variety of crops, including turf, as specified in the Directions for Use Table.



Kenso Corporation (M) Sdn Bhd 3C / 59 Oxford Street Bulimba QLD 4171 Phone (07) 3217 9788 www.kenso.com.au

IMPORTANT: READ THE ATTACHED LEAFLET BEFORE USE

CONTENTS: 20 Litres APVMA Approval No.: 69277/ 60398

KENSO AGCARE BIFENTHRIN TERMITICIDE & INSECTICIDE

STORAGE, SPILLAGE AND DISPOSAL

Store in the closed, original container in a cool, well-ventilated area. DO NOT store for prolonged periods in direct sunlight. Store in a locked room or place away from children, animals, food, feedstuffs, seed and fertilisers. In case of spillage, confine and absorb spilled product with absorbent material such as sand, clay or cat litter. Dispose of waste as indicated below or according to the Australian Standard AS 2507 – Storage and Handling of Pesticides. DO NOT allow spilled product to enter sewers, drains, creeks or any other waterways. Triple or preferably pressure rinse empty containers before disposal. Add rinsings to spray tank. DO NOT dispose of undiluted chemicals on-site. If recycling, replace cap and return clean containers to recycler or designated collection point. If not recycling, break, crush or puncture and bury empty containers in a local authority landfill. If no landfill is available, bury the containers below 500 mm in a disposal pit specifically marked and set up for this purpose clear of water ways, desirable vegetation and tree roots. Empty containers and product should not be burnt.

SAFETY DIRECTIONS - AGRICULTURAL CROPS

Poisonous if swallowed. Attacks eyes. Will irritate the skin. Avoid contact with eyes and skin. DO NOT inhale spray mist. When preparing spray, wear cotton overalls buttoned to the neck and wrist and washable hat, elbow-length PVC gloves and goggles. When using the prepared spray with hand held application equipment in bananas and grapes wear cotton overalls buttoned to the neck and wrist and elbow-length PVC gloves. If product in eyes, wash it out immediately with water. Wash hands after use. After each day's use, wash gloves, goggles and contaminated clothing.

SAFETY DIRECTIONS - PEST CONTROL

Poisonous if swallowed. Will damage eyes and will irritate the skin. Avoid contact with eyes and skin. DO NOT inhale vapour or spray. When opening container and preparing spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length PVC, neoprene or nitrile gloves, face shield or goggles and chemical resistant footwear. When using prepared spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length PVC, neoprene or nitrile gloves and chemical resistant footwear. When using in enclosed areas, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length PVC, neoprene or nitrile gloves, chemical resistant footwear and half-face respirator with the combined dust and gas cartridge. If clothing becomes contaminated with product or wet with spray, remove clothing immediately.

If product or spray on skin, immediately wash area with soap and water. If product in eyes, wash it out immediately with water. After use and before eating, drinking or smoking, wash hands, arms and face thoroughly with soap and water. After each day's use, wash gloves, face shield or goggles, respirator (if rubber wash with detergent and warm water) and contaminated clothing.

FIRST AID

If poisoning occurs, contact a doctor or Poisons Information Centre. Phone Australia 131126. If swallowed, do NOT induce vomiting. Give a glass of water. If in eyes, hold eyes open, flood with water for at least 15 minutes and see a doctor.

MATERIAL SAFETY DATA SHEET

Additional information is listed in the Material Safety Data Sheet which can be obtained from the supplier.

CONDITIONS OF SALE

Kenso Corporation (M) Sdn. Bhd. will not accept any responsibility whatsoever and howsoever arising and whether for consequential loss or otherwise in connection with the supply of these goods other than responsibility for the merchantable quality of the goods and such responsibilities mandatorily imposed by Statutes applicable to the sale or supply of these goods. To the extent allowed by such Statutes the liability of Kenso Corporation (M) Sdn. Bhd. is limited to the replacement of the goods or (at the option of Kenso Corporation (M) Sdn. Bhd.) the refund of the price paid and where possible sufficient part of the goods to enable proper examination being returned to Kenso Corporation (M) Sdn. Bhd. within thirty days of delivery.

In a Transport Emergency
Dial **000**Police or Fire Brigade

Product Of Malaysia







Batch No .:

Date of Manufacture:

POISON KEEP OUT OF REACH OF CHILDREN READ SAFETY DIRECTIONS BEFORE OPENING OR USING KENSO

Termiticide & Insecticide

ACTIVE CONSTITUENT: 100 g/L BIFENTHRIN SOLVENT: 567.5 g/L LIQUID HYDROCARBONS 50 g/L N-METHYL-2-PYRROLIDONE



For the protection of structures from subterranean termite damage, for the control of termites and a range of other urban pests, and for the control of various insect and mite pests in a variety of crops including turf, as specified in the Directions for Use Table

IMPORTANT: READ THIS LEAFLET BEFORE USE

APVMA Approval No: 69277/60398

DIRECTIONS FOR USE-AGRICULTURAL CROPS

Spider Mite

Citrus

Cotton

(Tetranychus lambi)

Leafeating Weevi

States

NSW.

WA

only

600-800

375 mL/ha1

of row

3.8 mL/100 m

days

NOT

CUT

FOR

NOT

FEED

COTTON

TRASH

LIVES

STOC

mL/ha

(Eutinophaea

bicristata Lea)

Native Budworm

Cotton Bollworm

Two Spotted Mite

urticae). Green Mirid

dilutus), Apple Dimpling Bug

(Helicoverpa

punctigera).

(Helicoverpa

(Tetranychus

(Creontiades

(Campylomma liebknechti)

False Wireworm

Sugarcane Worm

(Agrypnus variabilis)

(Pterohlaeus

alternatus),

armigera),



RESTRAINTS

mite control.

Kenso Corporation (M) Sdn Bhd 3C / 59 Oxford Street Bulimba QLD 4171 Phone (07) 3217 9788

INSECTICIDE RESISTANCE WARNING GROUP 3A INSECTICIDE For insecticide resistance management Kenso Agcare Bifenthrin Termiticide & Insecticide is a Group 3A insecticide. Some naturally occurring insect biotypes resistant to Kenso Agcare Bifenthrin Termiticide & Insecticide and other Group 3A insecticides may exist through normal genetic variability in any insect population. The resistant individuals can eventually dominate the insect population if Kenso Agcare Bifenthrin Termiticide & Insecticide or other Group 3A insecticides are used repeatedly. The effectiveness of Kenso Agcare Bifenthrin Termiticide & Insecticide on resistant individuals could be significantly reduced. Since occurrence of resistant individuals is difficult to detect prior to use, Kenso Agcare Pty Ltd accepts no liability for any losses that may result from the failure of Kenso

ALL USES

insects

Kenso Agcare Bifenthrin Termiticide & Insecticide may be subject to specific resistance management strategies. For further information contact your local supplier, Kenso Agcare Pty Ltd representative or local agricultural department agronomist.

Agcare Bifenthrin Termiticide & Insecticide to control resistant

Note: Helicoverpa armigera resistance in Northern NSW and Qld. To help contain pyrethroid resistance in H. armigera, the Summer Crop Insecticide Strategy, as developed by the Qld Department of Primary Industries and NSW Agriculture, should be adhered to. Failure to observe the strategy may result in widespread resistance affecting the future viability of Summer cropping.

cm in height. Aim to apply a total spray volume of 1 L/stool area. For

single sucker row configurations apply 28 L of solution per 100 metres of row in a band 0.5 m wide on each side of the row overlapping in the

centre. For double sucker row configurations apply 56 L of solution per

100 metres of row in a band 1m wide on each side of the double row with

Monitor mite population on old leaves particularly during hot dry

conditions. Apply Kenso Agcare Bifenthrin Termiticide & Insecticide as a

preventative rather than a curative treatment before damage occurs, and before mite numbers build up to damaging levels. Follow up applications may be required at 10-14 day intervals. Thorough coverage of the lower leaf surface is essential to ensure good control. Use a total spray volume

the spray pattern overlapping between the rows.

STORAGE, SPILLAGE AND DISPOSAL

Store in the closed, original container in a cool, well-ventilated area. DO NOT store for prolonged periods in direct sunlight. Store in a locked room or place away from children, animals, food, feedstuffs, seed and fertilisers. In case of spillage, confine and absorb spilled product with absorbent material such as sand clay or cat litter. Dispose of waste as indicated below or according to the Australian Standard AS 2507 - Storage and Handling of Pesticides. DO NOT allow spilled product to enter sewers, drains, creeks or any other waterways. Triple or preferably pressure rinse empty containers before disposal. Add rinsings to spray tank. DO NOT dispose of undiluted chemicals on-site. If recycling, replace cap and return clean containers to recycler or designated collection point. If not recycling, break, crush or puncture and bury empty containers in a local authority landfill. If no landfill is available, bury the containers below 500 mm in a disposal pit specifically marked and set up for this purpose clear of water ways, desirable vegetation and tree roots. Empty containers and product should not be burnt

If poisoning occurs, contact a doctor or Poisons Information Centre. Phone Australia 131126. If swallowed, do NOT induce vomiting Give a glass of water. If in eyes, hold eyes open, flood with water for at least 15 minutes and see a doctor.

MATERIAL SAFETY DATA SHEET

Additional information is listed in the Material Safety Data Sheet which can be obtained from the supplier.

CONDITIONS OF SALE

Kenso Corporation (M) Sdn. Bhd. will not accept any responsibility whatsoever and howsoever arising and whether for consequential loss or otherwise in connection with the supply of these goods other than responsibility for the merchantable quality of the goods and such responsibilities mandatorily imposed by Statutes applicable to the sale or supply of these goods. To the extent allowed by such Statutes the liability of Kenso Corporation (M) Sdn. Bhd. is limited to the replacement of the goods or (at the option of Kenso Corporation (M) Sdn. Bhd.) the refund of the price paid and where possible sufficient part of the goods to enable proper examination being returned to Kenso Corporation (M) Sdn. Bhd. within thirty days of delivery.

In a Transport Emergency Dial **000** Police or Fire Brigade



Kenso Corporation (M) Sdn. Bhd. 3C / 59 Oxford Street Bulimba QLD 4171 Phone (07) 32179788

APVMA Approval No.: 69277/60398

CROP	PEST	STATE	RATE	WHP	CRITICAL COMMENTS
Bananas	Banana Weevil	Qld,	<u>Seasonal</u>	1	Seasonal Program
	Borer	NSW,	<u>Program</u>	day	Twice per year Timing: Apply in October/November (Spring/earl
	(Cosmopolites	WA,	Stool		Summer) and March/April (late Summer/Autumn). Use the higher rat
	sordidus),	NT	Treatment		(concentration) when borer pressure or damage is high.
	Banana Rust Thrips	only	Method 050,000		Once per year Timing: Apply in October/November OR March/April.
	(Chaetanaphothrips		250-330		Monitoring Program: Monitor weevil borer populations carefully by tra
	signipennis)		mL/100 L		counts and/or corm damage ratings, beginning in September when pes
			twice per		activity is on the increase and continue until April. Apply treatment when Banana Weevil Borers reach or exceed acceptable threshold levels
			year OR		Monitor borer control after application and re-treat as required.
			660 mL/100 L		Banana Weevil Borer: Application should be made after rain or irrigation
			once per year		during periods of high adult borer.
			onee per year		Banana Rust Thrips: Application against Banana Weevil Borer will give
			Band		coincident rust thrips control, particularly when application is made when
			Treatment		thrips activity is on the increase usually beginning September and into
			Method		the Summer months.
			250 mL/100 L		APPLICATION METHOD
			twice per		Stool Treatment Application: Remove trash from the base of stools and
			year		apply 500-750 mL of spray solution to each stool, depending on stoo
					size. Treat the bottom 30 cm of each stool as well as the soil in a 30 cm
			Monitoring		band around each stool, ensuring thorough treatment of both butt(s) and
			<u>Program</u>		follower(s). Use the lower spray volume of 500 mL on small stools less
			Stool		than 50 cm across the entire base.
			<u>Treatment</u> Method		Band Treatment Application: Apply as a band application with a side
			330 mL/100 L		delivery boom and offset nozzles on both sides of the row with the sprare pattern positioned to spray 30 cm of soil on either side of the row and 30 cm.
			330 IIIL/ 100 L	l	pattern positioned to spray 30 cm of soil on either side of the row and 3

Band

WA

only

Treatment

40 mL/100 L

<u>Method</u> 250 mL/100 L

DO NOT use as a foliar spray in banana plantations, or in situations and orchards where mite predators are established and providing effective

of 300-500 L/ha. Apply as a broadcast ground rig application in a total water volume of 50-Faba Redlegged Earth beans States 200 L/ha or by air in a minimum total water volume of 20 L/ha. Apply to Subterranean (Halotydeus bare soil after conventional cultivation and sowing or onto well grazed or clover destructor), sprayed pasture after direct drilling. Treat infested paddocks after sowing Brown Pasture and before or soon after seedling emergence. Use the higher rate or Clove heavier infestations and for longer residual protection. Kenso Agcare Barley Looper (Ciampa arietaria) Canola, Bifenthrin Termiticide & Insecticide is compatible with some herbicides. See compatibility statement for details Field Blue Oat Mite 100 mL/ha Peas. (Penthaleus major) Lupins, Pasture Webworm Lucerne & (Hednota spp.) Wheat 200 mL/ha (Bryobia spp.) 100-200 Canola Use the 100 mL rate when pest pressure is low. Monitor adjacent habitat Vegetable Weevil (Listroderes difficilis) mL/ha and edges of the field for the presence of Vegetable Weevil prior to making a decision whether to spray. Monitor stone fruit orchards for Carpophilus Beetle as fruit approach maturity and become susceptable to attack. Apply Kenso Agcare Dilute Peaches, Carpophilus Beetles Nectarines. (Carpophillus spp.) States spraying Bifenthrin Termiticide & Insecticide as a dilute spray before beetles reach Plums. Apricots Concentrate damaging levels. Apply to the foliage and fruit of the trees. Continue to monitor beetle numbers and if necessary reapply Kenso Agcare Bifenthrin Termiticide & Insecticide up to 1 day before harvest or use spraving Refer to the mixing/ another insecticide registered for this purpose. Apply no more than 2 application applications per season. There must be a minimum of 10 days between the re-treatment and the initial application. Apply the same total amount section

days

prevent excessive build up of Carpophilus Beetle. Apply as a high volume band application in a 1.5 to 2 metres wide swath, to the ground, both sides of the row, under each tree. Aim to apply a total emergence program 12.5 or 25 spray volume of 5 to 10 L/tree (e.g. at 250 trees/ha = 1250 to 2500 L/ha). Pre-emergence program: Apply just prior to, or at the first sign of major beetle emergence in mid-October. Use the higher rate in blocks with a mL/tree history of high beetle numbers or when longer residual control is emergence required Post-emergence monitoring program: Apply at peak beetle monitoring emergence in October / November as indicated by field monitoring. program 6 mL/tree (Refer to monitoring statement on label). Follow up treatment may be

necessary based on a threshold of 25 beetles per 10 sites per orchard in consecutive counts 1-2 weeks apart. Apply as indicated by field checks. Use the higher rate when pest pressure is high, conditions favour pest development and when

of product to the target crop whether applying this product by dilute or concentrate spraying methods. DO NOT use rates greater than 100 mL/100 L of water when using concentrate spraying. Cultural control methods (eg. Destruction of fallen fruit by mulching) should be used to

increased residual protection is required. Budworm and Bollworm: Applications should be limited to coincide with egg hatch and when small larvae up to 5 mm are present. DO NOT apply **GRAZE** this product to Helicoverpa armigera larvae larger than 5 mm in length.

Two Spotted Mite: Applications against Helicoverpa spp. will give good control of coincident two spotted mite, particularly when applied on low mite population (around 10 % leaf infestation). If conditions continue to favour mite development a second application maybe required 14-20 **KFEED** days later.

Green Mirid & Apple Dimpling Bug: Apply at recommended threshold levels as indicated by field checks. Use the higher rate for increased pest pressure and longer residual protection.

Wireworm: Apply as a spray into the furrow at planting. Use a spray nozzle which will deliver a coarse spray in a total volume of 60-100 L/ha in a 10 cm band over the seed before the soil is brought in behind covering tyres in front of the press wheel.

1 The rate is based on a 1 m row spacing. If row spacing varies from 1 m then apply at the use rate according to mL/100 m of row.

CROP	PEST	STATE	RATE	WHP	CRITICAL COMMENTS	
Grapes	Fig Longicorn (Acalolepta vastator)	NSW, ACT, WA only	1000 mL/100 L	-	The application MUST be made at late dormancy after pruning and before bud burst. Apply a single high volume spray, with nozzles directing the spray solution to the trunk and cordons (arms) of grape vines to achieve thorough wetting of the bark. Total spray volume should be about 500 mL/vine achieved by hand application.	
Lucerne seed crops	Native Budworm (Helicoverpa punctigera)	All States	400-600 mL/ha	-	DO NOT treat lucerne seed crops for alfalfa sprout production. Apply indicated by field checks after the commencement of flowering. Use higher rate when pest pressure is high, conditions favour development and when increased residual protection is required. Native Budworm: Applications should be timed to coincide with hatch and when small larvae up to 5 mm are present.	
Navy Beans	Native Budworm (Helicoverpa punctigera), Corn Earworm (Helicoverpa armigera)	All States	600-800 mL/ha	14 days H and G	Apply as indicated by field checks from flowering onwards. Use the higher rate when pest pressure is high, conditions favour per development and when increased residual protection is required. Budworm and Earworm: Applications should be timed to coincide wife egg hatch and when small larvae up to 5 mm are present. DO NOT apply this product to Helicoverpa (= Heliothis) armigera larvae larger than 5 mm in length.	
Pears	Longtailed Mealybug (Pseudococcus longispinus)	Vic, WA only	25 mL/100 L plus the registered rate of a non-ionic surfactant	14 days	Examine wood for the presence of over wintering Longtailed Mealy Bug but do not spray until large numbers of young nymphs emerge in Sprin Apply this mixture to near the point of run-off to all above ground parts the tree between green tip to commencement of flowering. DO NC spray after flowering has commenced.	
Sugarcane	Sugarcane Wireworm (Agrypnus spp.)	Qld, NSW, WA only	375 mL/ha1 or 5.6 mL/100 m of row	ı	Apply as a spray into the furrow at planting. Use a spray nozzle which w deliver a coarse spray in a total volume of 60-100 L/ha in a band 20-3 cm wide over the base of the furrow on top of the setts and befor covering soil is brought in by tynes. 1 The rate is based on a 1.5 m row spacing. If row spacing varies fro 1.5 m then apply at the use rate according to mL/100 m of row.	
Tomatoes	Native Budworm (Helicoverpa punctigera), Corn Earworm (Helicoverpa armigera), Two Spotted Mite (Tetranychus urticae), Tomato Russet Mite (Aculops lycopersici)	All States	High Volume 40-60 mL/ 100 L or Low Volume 600 mL/ha	1 day	DO NOT use low volume ground or air application on trellis tomatoes. Crop Monitoring Program Helicoverpa spp.: Apply as indicated by field checks. Applications shou be timed to coincide with egg hatch and when small larvae up to 5 m are present. DO NOT apply this product to Helicoverpa (= Heliothis) armigera larva larger than 5 mm in length. Mites: Applications against Helicoverpa spp. will give good control coincident Mites, particularly when applied on low mite populations. conditions continue to favour mite development, a second application may be required 14-20 days later. Schedule Spray Program If fields are not checked during pest infestation periods, apply on a 7-1 day alternating program with a non pyrethroid insecticide. Use the high rate (high volume application) and shorter interval when pest infestatic is more severe and when increased residual protection is required. D NOT apply this product to Helicoverpa armigera larvae larger than 5 m in length.	
Turf	Whitefly (Trialeurodes vaporiorum) Lawn Army Worm	All	30 mL/100 L water 1.2 L/ha		Apply as indicated by pest incidence and repeat as necessary. Use total spray volume of 2500 L/ha. Mix Kenso Agcare Bifenthrin Termiticide & Insecticide in water and app	
full (for example Lawns, Commercial turf farms, Parks, Recreational areas, Bowling greens, Sports	(Spodoptera maurita), Sod Webworm (Herpetogramma licarsisalis) Argentine Stem Weevil adults (Listronotus bonariensis), Billbug adults (Senophorus sp.) African Black Beetle	States	(12 mL/100 m2) 1.2-2.4 L/ha (12-24 mL/100 m2)		evenly over the area to be treated using spray application equipmer Use a minimum total spray volume of at least 200 L/ha (2 L/100 m2). I ensure optimal control, irrigate the treated area with up to 4 mm of wat soon after application. Inspect treated areas for continuing activity. Reapply as required. Whe a rate range is indicated use lower rates under lower insect pressure ar higher rates under higher insect pressure. Apply after mowing minimise loss of insecticide in clipping. DO NOT apply to soils if excessively wet or immediately after heavy rain	
fields)	adults (Heteronychus arator) Black Ant,	-	(24-36 mL/100 m2) 1.2-4.4 L/ha		Mix Kenso Agcare Bifenthrin Termiticide & Insecticide in water and app	
	Coastal Brown Ant, Funnel Ant, Meat Ant, Sugar Ant and Stinging Ant only		(12-44 mL/100 m2)		evenly over the area to be treated using spray application equipmer Apply to areas where ants are active. Where possible spray directly in the nests. Use the low rate for maintenance treatments or to control lig infestations and the high rate for heavy infestations and for maximu residual control. The elimination of funnel ants from a particular site w generally require more than one application. Initial applications should be applied over effected areas. As the initi numbers of active colonies is reduced, application should shift targetin active mounds. Apply spray directly to the mound and in the are	

NOT TO BE USED FOR ANY PURPOSE, OR IN ANY MANNER, CONTRARY TO THIS LABEL UNLESS AUTHORISED UNDER APPROPRIATE LEGISLATION.

immediately surrounding active mounds (300 mm radius).

<u>WITHHOLDING PERIODS:</u>
APRICOTS, NECTARINES, PEACHES, PLUMS, TOMATOES: DO NOT HARVEST FOR 1 DAY AFTER APPLICATION.

FOR GROUND APPLICATIONS:-DO NOT HARVEST FOR 1 DAY AFTER APPLICATION. FOR FOLIAR APPLICATIONS: DO NOT HARVEST FOR 8 DAYS AFTER APPLICATION.

COTTON: DO NOT HARVEST FOR 14 DAYS AFTER APPLICATION. DO NOT GRAZE OR CUT FOR STOCK FEED. DO NOT FEED COTTON TRASH TO LIVESTOCK.

DO NOT HARVEST FOR 14 DAYS AFTER APPLICATION.

DO NOT HARVEST, GRAZE OR CUT FOR STOCK FEED FOR 14 DAYS AFTER APPLICATION.

BARLEY, CANOLA, FABA BEANS, FIELD PEAS, LUCERNE, LUPINS, SUBTERRANEAN CLOVER, WHEAT: DO NOT GRAZE OR CUT FOR STOCK FOOD FOR 4 WEEKS AFTER APPLICATION. HARVEST WHP NOT REQUIRED WHEN USED AS DIRECTED.

CITRUS, GRAPES, SUGARCANE: NOT REQUIRED WHEN USED AS DIRECTED.

DIRECTIONS FOR USE- PEST CONTROL USES

DO NOT use this product at less than indicated label rates. Restraints:

DO NOT apply to soils if excessively wet or immediately after heavy rain to avoid run-off of the chemical

PEST	SITUATION	STATE	RATE	CRITICAL COMMENTS
Spiders	External Areas & Surrounds of Domestic, Commercial, Public & Industrial buildings and structures	All States	25-50 mL/ 10 L	Use the higher rate in situations where pest pressure is high, when rapid knockdown and/or maximum residual protection is desired. Pay particular attention to protected dark areas such as cracks and crevices, under floors, eaves and other known hiding or resting places. For overal band surface spray, apply as a coarse, low pressure surface spray to areas where spiders hide frequent and rest. Spray to the point of run-off using around 5 L of spray mixture per 100 m² and ensuring thorough coverage of the treated surfaces. For crack and crevice treatment use ar appropriate solid stream nozzle. For Maximum spider control use a two part treatment. 1. Crack and crevice. 2. Overall band spray of surfaces.
Papernest Wasps			50 mL/ 10 L	Apply prepared emulsion to the point of run-off directly to the papernest ensuring thorough and even coverage. When all adult wasps have been knocked-down the nest may be safely removed from the structure.
Ants, Cockroaches, Mosquitoes, Fleas, Flies, Ticks (excluding the paralysis tick Ixodes holocyclus) (Adults & Nymphs)			50- 100 mL/ 10 L	On non-porous surfaces apply as a coarse spray at the rate of 1 L of emulsion per 20 m². Wher treating non-porous surfaces do not exceed the point of run-off. On porous surfaces or use through power equipment, spray at the rate of 1 L of emulsion per 10 m². When treating porous surfaces do not exceed the point of run-off. Use the higher rate in situations where pest pressure is high, when rapid knockdown and/or maximum residual protection is desired. The lower rate may be used for follow-up treatments. To control ants apply to trails and nests. Repeat as necessary. To control fleas and ticks apply prepared emulsion to outside surfaces of buildings and surrounds including but not limited to foundations, verandas, window frames, eaves, patios garages, pet housing, soil, turf, trunks of woody ornamentals or other areas where pests congregate or have been seen. To control flies and mosquitoes apply prepared emulsion to surfaces where insects rest or harbour. Reapply as necessary. For perimeter treatments apply the prepared emulsion to a band of soil or vegetation two to three meters wide around and adjacent to the structure. Also treat the foundation of the structure to a height of approximately one metre. Use a spray volume of 5 to 10 L per 100 m². Higher volumes of water may be needed if organic matter is present or foliage is dense.
Subterranean Termites	Domestic, Commercial, Public and Industrial buildings and structures. Service poles, fence posts and nest eradication	All States, except Tas	Refer to Table A	Refer to Table B.

TABLE A: KENSO AGCARE BIFENTHRIN TERMITICIDE & INSECTICIDE USE RATES FOR CONTROL OF SUBTERRANEAN

All areas SOUTH of the Tropic of Capricorn (except Tas)		
Rate	Expected Protection period	
1.0 L/ 100 L	At least 10 years	
500 mL/ 100 L	10 years	
250 mL/ 100 L	3 years	
1.0 L/ 100 L	At least 10 years	
500 mL/ 100 L	10 years	
500 mL/ 100 L	10 years	
500 mL/ 100 L	Not Applicable	
All areas NORTH of the Tropic of Capricorn		
Rate	Expected Protection period	
1.5L/ 100L	Up to 5 years	
1.0 L/ 100 L	Up to 4 years	
750 mL/ 100 L	Up to 3 years	
1.5L/ 100L	Up to 5 years	
1.0 L/ 100 L	Up to 4 years	
750 mL/ 100 L	Up to 3 years	
500 mL/ 100 L	Up to 2 years	
1.5L/ 100L	Up to 5 years	
1.0 L/ 100 L	Up to 4 years	
750 mL/ 100 L	Up to 3 years	
500 mL/ 100 L	Not Applicable	
	Rate 1.0 L/ 100 L 500 mL/ 100 L 250 mL/ 100 L 500 mL/ 100 L 500 mL/ 100 L 500 mL/ 100 L 500 mL/ 100 L All areas NORTH of the Rate 1.5L/ 100L 750 mL/ 100 L 750 mL/ 100 L	

The length of the protection period is determined by a variety of factors including termite hazard, climate, soil conditions and the rate of the termiticide applied. These factors should be taken into consideration when evaluating the need for retreatment. Annual inspections by a competent Pest Control Operator are recommended to determine the need for further termite management options. Under high termite challenge, more

frequent inspections are advised

TABLE B: CRITICAL COMMENTS for use against SUBTERRANEAN TERMITES

	TICAL COMMENTS for use against SUBTERRANEAN TERMITES
Situations	Critical Comments
Perimeter Barriers – Existing buildings	 Perimeter barriers (both horizontal and vertical, external and , where appropriate, internal and subfloor) are essential for effective termite protection. Perimiter barriers should be installed around slabs, piers, substructure walls and external penetration points upon completion of the building. Apply using suitable equipment to form a continuous (horizontal and vertical) chemical barrier to a depth of 80 mm below the top of foots around the structure. Formation of the barrier may require several application techniques, including soil trenching and/or rodding and open wand application. Chemical barriers which have been disturbed by construction, excavation or landscaping should be reapplied to restore continuity of the barrier.
Post- construction Barrier Treatment – Management of termites in existing buildings	Apply with suitable application equipment to form a continuous vertical and horizontal chemical barrier around and under the structure with particular emphasis on known infestation areas. The formation of the barrier may require a combination of several application techniques, including trenching, soil rodding, sub-slab injection and open wand applications. Chemical barriers beneath concrete slabs, paths, driveways, etc. will require concrete drilling. Holes should be drilled 150 to 300 mm apart and no more than 150 mm from walls or expansion joints. To enhance soil distribution, use a lateral dispersion tip on the injector and apply up to 10 L of emulsion per linear metre. For areas beneath suspended floors with inadequate access (i.e. less than 400 mm clearance), the entire subfloor area should be treated as a continuous horizontal barrier which completely abuts any internal vertical barriers around substructure walls. Otherwise, install perimeter barriers around each individual pier, stump, penetration point and substructure wall. Chemical barriers that have been disturbed by construction, excavation or landscaping should be reapplied to restore continuity of the barrier.
Protection of Service Poles and Fence Posts	 Create a continuous termiticide barrier 450 mm deep and 150 mm wide around the pole or post by soil injection or rodding. For new poles and posts, treat backfill and the bottom of the hole. Use 100 L of emulsion per m³ of soil. Regular inspections should be undertaken to determine when and if retreatment is necessary. If disturbance of the barrier has occurred, retreatment of the area affected will be required. Posts and poles may also be drilled and injected with spray solution. Note: For existing poles and posts, it is impractical to treat the full depth and underneath of such poles and posts and therefore the possibility of future termite attack from below the treated area cannot be ruled out.
Eradication of Termite Nest	• Locate nest and flood with insecticide emulsion. Trees, poles, posts and stumps containing nests may require drilling prior to treatment with termiticide emulsion. The purpose of drilling is to ensure the termiticide emulsion is distributed throughout the entire nest. Drill holes in live trees should be sealed with an appropriate caulking compound after injection.

Note: The termiticide barrier provided by this product has a finite life. This, together with the recommendation to undertake annual inspections, must be stated on a durable notice as required by BCA B1.3(j)(ii).

NOT TO BE USED FOR ANY PURPOSE, OR IN ANY MANNER, CONTRARY TO THIS LABEL UNLESS AUTHORISED UNDER APPROPRIATE LEGISLATION.

GENERAL INSTRUCTIONS- AGRICULTURAL CROPS

Kenso Aggare Bifenthrin Termiticide & Insecticide is a contact and residual insecticide/miticide. It can be used as a protective treatment when applied at regular intervals or as a knockdown treatment to control existing pests. Best results are obtained when Kenso Agcare Bifenthrin Termiticide & Insecticide is applied before pest populations build up to damaging levels. This product is not suitable for use in Integrated Pest Management (IPM) programs where mite predators are established and providing effective mite control.

Kenso Agcare Bifenthrin Termiticide & Insecticide may be applied by either ground rig or aircraft. Thorough coverage is essential to ensure adequate control. DO NOT apply as a fog or mist.

Dilute Spraving:

- · Use a sprayer designed to apply high volumes of water up to the point of run-off and matched to the crop being sprayed. · Set up and operate the sprayer to achieve even coverage throughout the crop canopy. Apply sufficient water to cover the crop to the point of run-off.
- The required water volume may be determined by applying different test volumes, using different settings on the sprayer, from industry guidelines or expert advice.
- Add the amount of product specified in the Directions for Use table for each 100 L of water. Spray to the point of run-off.
- The required dilute spray volume will change and the sprayer set up and operation may also need to be changed, as the crop grows, Concentrate Spraying:
- (a) Use a sprayer designed and set up for concentrate spraying (that is a sprayer which applies water volumes less than those required to reach the point of run-off) and matched to the crop being sprayed.
- (b) Set up and operate the sprayer to achieve even coverage throughout the crop canopy using your chosen water volume.
- (c) Determine an appropriate dilute spray volume (See Dilute Spraying above) for the crop canopy. This is needed to calculate the concentrate mixing
- (d) The mixing rate for concentrate spraying can then be calculated in the following way: Example only;
- 1. Dilute spray volume as determined above: For example 1000 L/ha. 2. Your chosen concentrate spray volume: For example 500 L/ha.
- 3. The concentration factor in this example is: $2 \times (ie. 1000 \text{ L} 500 \text{ L} = 2)$.
- 4. If the dilute label rate is 50 mL/100 L, then the concentrate rate becomes 2 x 50, that is 100 mL/100 L of concentrate spray.

The chosen spray volume, amount of product per 100 L of water, and the sprayer set up and operation may need to be changed as the crop grows. For further information on concentrate spraying, users are advised to consult relevant industry guidelines, undertake appropriate competency training and follow industry Best Practices.

Ground Application:

Applications should be made as a fine spray preferably using hollow cone nozzles and a droplet size of 150 to 200 microns. The application volume will depend on the type of crop to be treated. The following are suggested:

Low volume broadacre applications to - e.g. cereals, canola, grain legumes, lucerne, subterranean clover: 50-200 L/ha.

Low volume row crops applications to tomatoes & navy beans: 50-200 L/ha.

High volume applications to row crops - e.g. trellised tomatoes: 200-1000 L/ha except as noted in critical comments. Use 200 L/ha from transplanting increasing to 1000 L/ha at maturity.

High volume directed spray:

Grapes: Apply by hand application, using a high volume coarse spray of 500 mL/vine (e.g. at approx. 2500 vines/ha = 1250 L/ha). High volume application to Stone Fruits: 1000 to 2000 L/ha

Foliar sprays to bananas: 300 to 500 L/ha.

Soil Applied Sprays:

High volume application

Stool treatment: Apply as a coarse spray at 500-750 mL per stool.

Band treatment: Apply as a band application with a side delivery boom and offset nozzles – 1 L of spray solution per stool.

Citrus: Apply as a high volume, directed spray to the ground under each tree. For optimum control apply to both sides of the tree. Total spray volume should be 5 to 10 L/tree (e.g. at 250 trees/ha = 1250 to 2500 L/ha).

Cotton, Sugarcane: Use a coarse spray: 60 to 100 L/ha as a band over the seed or sett before covering with soil - refer to critical comments for details. Aerial Application: Use at least 20 L/ha of total spray volume. Spray during the cooler parts of the day or night. To reduce possibility of drift avoid spraying in calm conditions or when wind is light and variable. Preferably, spray in a crosswind. Use suitable application equipment and/or nozzles to deliver a fine spray with a droplet size of 150 to 200 microns. A spraydrift minimisation strategy should be employed at all times when aerially applying sprays to, or near, sensitive areas. The strategy envisaged is best exemplified by the cotton industry's Best Management Practice manual MONITORING

Post-emergence monitoring of Citrus leafeating weevil populations: At first sign of major beetle emergence in mid October commence monitoring at 1 to 2 week intervals. Place polystyrene fruit box (330 x 480 mm) under tree, shake branches vigorously, repeat on ten randomly selected trees throughout orchid. If 25 beetles or more are recorded in consecutive counts, treatment is required

Add the required quantity of Kenso Agcare Bifenthrin Termiticide & Insecticide to water in the spray tank and mix thoroughly. Maintain agitation during mixing

and application

Kenso Agcare Bifenthrin Termiticide & Insecticide is compatible with commonly used fungicides such as Mancozeb 800 g/kg, Antracol+ and the herbicides -Paraquat 135 g/L/Diquat 115 g/L, Broadstrike+, Spinnaker+, Simazine 900 g/kg, Dual+, Metribuzin 480 g/L, Chlorsulfuron 750 g/kg, Triasulfuron 750 g/kg and Pendimethalin 330 g/L

SURFACTANTS

Kenso Agcare Bifenthrin Termiticide & Insecticide contains a surfactant. Additional surfactant may only be necessary on hard to wet plants and in high volume situations

STONE FRUIT EXPORT ADVICE

Export of Treated Stone Fruit - Some export markets do not have suitable Maximum Residue Limits or Import Tolerances in place. Please contact Kenso Agcare or the Australian Fresh Stone Fruit Growers Association prior to using this product on crops destined for export

RE-ENTRY TO TREATED FIELDS/CROPS DO NOT re-enter treated field/crop until spray deposits have dried, unless wearing suitable protective clothing (i.e. waterproof hat, overalls, boots and gloves)

PROTECTION OF WILDLIFE, FISH, CRUSTACEANS AND THE ENVIRONMENT

Dangerous to fish and aquatic organisms. DO NOT contaminate dams, rivers, streams, waterways or drains with product or the used container. Tail drains which flow from treated areas should be prevented from entering river systems.

PROTECTION OF LIVESTOCK

Dangerous to bees. DO NOT spray any plants in flower when bees are foraging. Spray in the early morning when bees are not actively foraging.

SAFETY DIRECTIONS - AGRICULTURAL CROPS

Poisonous if swallowed, Attacks eyes, Will irritate the skin, Avoid contact with eyes and skin, DO NOT inhale spray mist. When preparing spray, wear cotton overalls buttoned to the neck and wrist and washable hat, elbow-length PVC gloves and goggles. When using the prepared spray with hand held application equipment in bananas and grapes wear cotton overalls buttoned to the neck and wrist and elbow-length PVC gloves. If product in eyes, wash it out immediately with water. Wash hands after use. After each day's use, wash gloves, goggles and contaminated clothing.

GENERAL INSTRUCTIONS- PEST CONTROL

Pest Control - Kenso Agcare Bifenthrin Termiticide & Insecticide is a powerful knockdown and residual pesticide. Ants, cockroaches, fleas, flies, mosquitoes, spiders, ticks and wasps are controlled by direct contact with spray and also by residual action as they come into contact with treated surfaces.

Termites - The use of Kenso Agcare Bifenthrin Termiticide & Insecticide ticide will help prevent and control subterranean termite infestations in and around structures, service poles and fence posts. A dilute termiticidal emulsion must be adequately dispersed into the soil to establish both horizontal and vertical barriers between the structure to be protected and subterranean termites in the soil. The purpose of external and vertical termite barriers, which are an essential part of the treatment, is to prevent concealed termite entry into the structure. The horizontal and vertical chemical barriers must be placed in accordance with the Australian Standard AS 3660 series. For treatment of existing buildings, both horizontal and vertical barriers may be required around under the buildings. Barriers must provide a continuous, no gap zone of protection between the structure and the termite colony. Therefore, it is essential that the barrier be established by a Pest Control Operator familiar with the construction details of the building. Further details are provided in the "Horizontal Barrier Treatment" and "Vertical Barrier Treatment" sections of this label and in the Australian Standard AS 3660 Series.

Horizontal Barrier Treatments: Use 5 L of emulsion per m2 of soil. Apply the diluted Kenso Agcare Bifenthrin Termiticide & Insecticide mixture to the soil surface evenly so that a continuous barrier with no gaps is formed. To minimize drift, use low pressure, high volume spray equipment delivering large droplets On impervious soils, where the application of 5 L diluted mixture per m2 would result in run-off, the total volume of mixture applied may be reduced provided $the concentration of Kenso Agcare \ Bifenthr in Termit icide \& Insecticide in the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly, e.g. if the intended rate of application is 1.0 L/100 and the mixture is increased accordingly according$ L, and the amount of spray applied is halved (2.5 L/m2), the concentration of Kenso Agcare Bifenthrin Termiticide & Insecticide should be doubled to 1.0 L/50 L (or 2.0 L/100 L). DO NOT apply less than 2 L diluted mixture per m2. In situations where the soil surface is very dry and conditions are conducive to rapid drying, the area to be treated should be moistened prior to the termiticide application.

Vertical Barrier Treatment: To install a vertical barrier, use a minimum of 100 L diluted mixture per m3 of soil. Vertical barriers must be a minimum of 150 mm wide, extend 80 mm below the top of footings and must be continuous with no gaps. Vertical barriers can be formed by trenching to the required depth and treating the soil as the trench is backfilled, by soil rodding or by the use of reticulation systems, as described in the Australian Standard AS 3660 Series. When using the soil rodding method to establish a vertical barrier, use the distance between rod spacings given in the table below. Loosen soil to a depth of 150 mm to improve soil penetration.

Soil Type	Rod Spacing (mm)
Heavy Clay	150
Clay Loams	200
Loams	250
Sands	300

Perimeter Barrier Treatments: Perimeter barriers consist of horizontal barriers at least 150 mm wide adjoining a vertical barrier of at least 150 mm in width. A perimeter barrier must completely surround all buildings/structures, pipes, piers, and service penetrations. In buildings with suspended floors with greater than 400 mm crawl space, perimeter barriers should be installed to surround piers, stumps and service penetrations and completely abut all substructure walls. To ensure a continuous barrier, use at least 100 L of diluted mixture per m3 of soil. This can be achieved by applying 5 L diluted mixture per linear metre for a 300 mm deep vertical barrier or 10 L diluted mixture per linear metre for a 600 mm deep vertical barrier. Treat both sides of single brick walls down to the footing to prevent termites gaining access behind engaged piers.

Post-Construction Treatments under Concrete Slabs: For concrete slabs, the diluted mixture may be injected through holes drilled in the slab at intervals between 150 mm and 300 mm. Recommended spacings between holes is given in the table below

Soil Type	Hole Spacing (mm)	Litres per hole
Heavy Clay	150	1.5
Clay loams	200	2
Loams	250	2.5
Sands	300	3

Insecticide must only be made after thorough inspection of the building and after full assessment of termite activity. Equipment used for injection of Kenso Agcare Bifenthrin Termiticide & Insecticide into pre-drilled holes indoors must be in good working order, without any leaks and must be fitted with a working tip shut-off to prevent nozzle dripping. Drill holes must be resealed after injection.

Treatment in conjunction with Physical Barriers: In situations where the termite management system includes physical and chemical barriers, each certified system must be installed according to the relevant and appropriate specifications for the product and the Australian Standard AS 3660 series. Service Requirements

Service requirements can only be determined following inspection by a licensed Pest Control Operator as Subterranean termites are capable of bridging termite barriers. Inspections, in accordance with the Australian Standard AS 3660 series, should be conducted at least annually with more frequent inspections being required in high-risk termite areas. Such regular inspections increase the probability of detecting termite activity before damage requiring costly repairs occurs. Determination of the need for servicing requires consideration of factors such as termite pressure, integrity of the barrier and age and longevity of the termiticide applied. Several factors contribute to longevity of the termite treatment and must be considered when evaluating the need for retreatment. The actual protection period will depend on the termite hazard, climate, soil conditions and rate of termiticide used. Refer to Table A for the expected protection periods provided.

Add the required quantity of Kenso Agcare Bifenthrin Termiticide & Insecticide to water in the spray tank and mix thoroughly. Maintain agitation during both mixing and application. To facilitate even application of the diluted spray mixture over the area to be treated, the addition of a marker dye at label rates is recommended. On hard to wet soils, the penetration of the diluted spray mixture may be improved by the addition of a soil surfactant at label rates. PRECAUTIONS AND RE-ENTRY PERIOD - PEST CONTROL

DO NOT spray directly on humans, pets or animals. Avoid contact with food, food utensils or preparation surfaces. Re-entry Period – Pest Control

DO NOT allow people and pets to enter treated areas until the spray has dried. When prior entry is necessary, wear cotton overalls buttoned to the neck, wrist and elbow-length PVC, neoprene or nitrile gloves and chemical resistant footwear. Clothing must be laundered after each day's use.

PROTECTION OF WILDLIFE, FISH, CRUSTACEANS AND THE ENVIRONMENT Dangerous to fish and aquatic organisms. DO NOT contaminate dams, rivers, streams, waterways or drains with product or the used container.

PROTECTION OF PETS AND LIVESTOCK

Before spraying, remove animals and pets from the areas to be treated. Cover or remove any open food and water containers. Cover or remove fish ponds,

aquariums etc before spraying. SAFETY DIRECTIONS - PEST CONTROL

Poisonous if swallowed. Will damage eyes and will irritate the skin. Avoid contact with eyes and skin. DO NOT inhale vapour or spray. When opening container

and preparing spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length PVC, neoprene or nitrile gloves, face shield or goggles and chemical resistant footwear. When using prepared spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length PVC, neoprene or nitrile gloves and chemical resistant footwear. When using in enclosed areas, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length PVC, neoprene or nitrile gloves, chemical resistant footwear and half-face respirator with the combined dust and gas cartridge. If clothing becomes contaminated with product or wet with spray, remove clothing immediately. If product or spray on skin. immediately wash area with soap and water. If product in eyes, wash it out immediately with water. After use and before eating, drinking or smoking, wash hands, arms and face thoroughly with soap and water. After each day's use, wash gloves, face shield or goggles, respirator (if rubber wash with detergent and warm water) and contaminated clothing.